



# Gütermann creativ



EN



Degree of difficulty

## Instruction **PATCHWORK THROW**

# Instruction PATCHWORK THROW



## Materials from Gütermann

- Sew-all thread in a matching shade
- Cotton fabric 145 cm wide, collection SUMMER LOFT:
- 0.20 m each of  
flower ornament fabric in pink,  
rose pattern fabric in green-white,  
flower fabric in white-pink,  
spot fabric in pink-white,  
rose pattern fabric in white-pink,  
cloverleaf fabric in pink,  
ornament fabric in pink,  
rose pattern fabric in pink-white,
- 0.90 m meander pattern in pink
- 4.20 m bias binding in pink

## In addition

- 1.20 m iron-on volume fleece  
HH 650, 90 cm wide

## Tools

- Sewing machine
- Iron
- Pins
- Scissors
- Hand gauge
- Tape measure

## Cutting

Cut 48 squares 16 x 16 cm from each of the 8 fabrics

Backing: meander fabric in pink and volume fleece HH 650 each 90 x 120 cm



- 1.** Arrange the squares in any order with 6 rows of 8 squares on a table or on the floor to best see the distribution of the patterns.



**2.** For the first row lay 2 neighbouring squares together, right sides facing and sew them together with a 1 cm wide seam. Iron the seam allowances to one side. Piece all 8 squares to a row.



**3.** Also join the squares of the next 5 rows in the same way. Iron the seam allowances to one side. Now join the rows:

Lay the long edges of the first two rows together, right sides facing. Attach the edges with pins and sew the seam 1 cm from the cut edge. Also iron these seam allowances to one side. Sew together all 6 rows for the throw.



**4.** Now layer the fabrics and the fleece together like a sandwich: lay the back on the table with the right side facing downwards, followed by the double-sided coated volume fleece. Cover these two layers with the patchwork layer with the right side facing upwards.

Iron all three layers together. For optimum fusing of the layers lay a damp cloth on the layers and press the iron down in sections for 15 seconds each on cotton setting. Cut the edges exactly all the way around.



**5.** Sew the edges of the three layers of fabric together set to large stitches (4-6 mm) at presser foot width from the outer edge. This makes it easier to enclose the edges with bias binding. For the long sides fold approx. 4.30 m of bias binding and iron the edge in. Then unfold the binding. Pin the binding along the edges starting from one corner with right sides facing. When one piece of binding ends then slide the beginning of the next piece, folded over for 1 cm, under the end. Lay a fold into the corners. Sew the bias binding along the iron fold through all layers. Then fold the bias binding with the folded seam allowance around the edges and pin it in place, also lay angled folds here in the corners.



**6.** Sew the beginning of the bias binding for approximately 10 cm from the 1st corner close to the edge and through all layers. Now turn the end of the bias binding to the right side at this corner: fold the bias binding together with right sides facing and pin the layers together. Sew the seam along the outer edge of the bias binding that is already sewn. Cut the threads and trim the seam allowances. Turn the corner to the right side so that the seam allowances are on the inside and the beginning of the enclosed edge is now covered with bias binding.



**7.** Sew all around the throw close to the edge along the fold edge of the bias binding from the right side. Ensure that the seam always catches all the layers.

**Gütermann GmbH**

Landstr. 1

DE- 79261 Gutach-Breisgau

Tel +49 76 81 21-0

Fax +49 76 81 21-449

mail@guetermann.com

[www.guetermann.com](http://www.guetermann.com)

